



Scoring I

Makoto Asai (SLAC)
Geant4 Tutorial Course

Geant 4

Contents

- Retrieving information from Geant4
- Command-based scoring
- Add a new scorer/filter to command-based scoring
- Define scorers in the tracking volume
- Accumulate scores for a run



Retrieving information from Geant4


Geant 4

Extract useful information

- Given geometry, physics and primary track generation, Geant4 does proper physics simulation “silently”.
 - You have to add a bit of code to **extract information useful to you**.
- There are three ways:
 - Built-in scoring commands
 - Most commonly-used physics quantities are available.
 - Use scorers in the tracking volume
 - Create scores for each event
 - Create own Run class to accumulate scores
 - Assign **G4VSensitiveDetector** to a volume to generate “hit”.
 - Use user hooks (G4UserEventAction, G4UserRunAction) to get event / run summary
- You may also use user hooks (G4UserTrackingAction, G4UserSteppingAction, etc.)
 - You have full access to almost all information
 - Straight-forward, but do-it-yourself



This talk



Command-based scoring

Geant 4





Command-based scoring

- Command-based scoring functionality offers the built-in scoring mesh and various scorers for commonly-used physics quantities such as dose, flux, etc.
 - Due to small performance overhead, it does not come by default.
- To use this functionality, access to the G4ScoringManager pointer after the instantiation of G4RunManager in your *main()*.

```
#include "G4ScoringManager.hh"
int main()
{
    G4RunManager* runManager = new G4RunManager;
    G4ScoringManager* scoringManager =
        G4ScoringManager::GetScoringManager();
    ...
}
```

- All of the UI commands of this functionality are in /score/ directory.
- /examples/extended/runAndEvent/RE03

Command-based scorers



Define a scoring mesh

- To define a scoring mesh, the user has to specify the followings.
 1. **Shape and name** of the 3D scoring mesh.
 - Currently, box and cylinder are available.
 2. Size of the scoring mesh.
 - Mesh size must be specified as "**half width**" similar to the arguments of G4Box / G4Tubs.
 3. **Number of bins** for each axes.
 - Note that too many bins causes immense memory consumption.
 4. Optionally, position and rotation of the mesh.
 - If not specified, the mesh is positioned at the center of the world volume without rotation.

```
# define scoring mesh
/score/create/boxMesh boxMesh_1
/score/mesh/boxSize 100. 100. 100. cm
/score/mesh/nBin 30 30 30
```

- The mesh geometry can be completely independent to the real material geometry.

Scoring quantities


- A mesh may have arbitrary number of scorers. Each scorer scores one physics quantity.
 - energyDeposit * Energy deposit scorer.
 - cellCharge * Cell charge scorer.
 - cellFlux * Cell flux scorer.
 - passageCellFlux * Passage cell flux scorer
 - doseDeposit * Dose deposit scorer.
 - nOfStep * Number of step scorer.
 - nOfSecondary * Number of secondary scorer.
 - trackLength * Track length scorer.
 - passageCellCurrent * Passage cell current scorer.
 - passageTrackLength * Passage track length scorer.
 - flatSurfaceCurrent * Flat surface current Scorer.
 - flatSurfaceFlux * Flat surface flux scorer.
 - nOfCollision * Number of collision scorer.
 - population * Population scorer.
 - nOfTrack * Number of track scorer.
 - nOfTerminatedTrack * Number of terminated tracks scorer.

/score/quantitly/xxxxx <scorer_name> <unit>

Scoring 1 - M.Asari (SLAC)

List of provided primitive scorers

- Concrete Primitive Scorers (See Application Developers Guide 4.4.6)
 - Track length
 - G4PSTrackLength, G4PSPassageTrackLength
 - Deposited energy
 - G4PSEnergyDeposit, G4PSDoseDeposit, G4PSChargeDeposit
 - Current/Flux
 - G4PSFlatSurfaceCurrent, G4PSSphereSurfaceCurrent, G4PSPassageCurrent, G4PSFlatSurfaceFlux, G4PSCellFlux, G4PSPassageCellFlux
 - Others
 - G4PSMinKinEAtGeneration, G4PSNofSecondary, G4PSNofStep



Filter

- Each scorer may take a filter.
 - charged * Charged particle filter.
`/score/filter/kineticEnergy <fname> <eLow> <eHigh> <unit>`
 - neutral * Neutral particle filter.
`/score/filter/particle <fname> <p1> ... <pn>`
 - kineticEnergy * Kinetic energy filter.
 - particle * Particle filter.
 - particleWithKineticEnergy * Particle with kinetic energy filter.

```
/score/quantity/energyDeposit eDep MeV
/score/quantity/nOfStep nOfStepGamma
/score/filter/particle gammaFilter gamma
/score/quantity/nOfStep nOfStepEMinus
/score/filter/particle eMinusFilter e-
/score/quantity/nOfStep nOfStepEPlus
/score/filter/particle ePlusFilter e+
```

Same primitive scorers
with different filters
may be defined.

`/score/close`



Close the mesh when defining scorers is done.

Drawing a score

- Projection

`/score/drawProjection <mesh_name> <scorer_name> <color_map>`

- Slice

`/score/drawColumn <mesh_name> <scorer_name> <plane> <column>
<color_map>`

- Color map


- By default, linear and log-scale color maps are available.
- Minimum and maximum values can be defined by `/score/colorMap/setMinMax` command. Otherwise, min and max values are taken from the current score.

Write scores to a file

- Single score
 /score/dumpQuantityToFile <mesh_name> <scorer_name> <file_name>
- All scores
 /score/dumpAllQuantitiesToFile <mesh_name> <file_name>
- By default, values are written in CSV.
- By creating a concrete class derived from G4VScoreWriter base class, the user can define his own file format.
 - Example in /examples/extended/runAndEvent/RE03
 - User's score writer class should be registered to G4ScoringManager.

More than one scoring meshes

- You may define more than one scoring mesh.
 - And, you may define arbitrary number of primitive scorers to each scoring mesh.
- Mesh volumes may overlap with other meshes and/or with mass geometry.
- A step is limited on any boundary.
- Please be cautious of too many meshes, too granular meshes and/or too many primitive scorers.
 - Memory consumption
 - Computing speed





Add a new scorer/filter to command-based scorers


Geant 4

Scorer base class

- G4VPrimitiveScorer is the abstract base of all scorer classes.
- To make your own scorer you have to implement at least:
 - Constructor
 - Initialize()
 - Initialize G4THitsMap<G4double> map object
 - ProcessHits()
 - Get the physics quantity you want from G4Step, etc. and fill the map
 - Clear()
 - GetIndex()
 - Convert **three copy numbers** into an index of the map
- G4PSEnergyDeposit3D could be a good example.
- Create your own messenger class to define /score/quantity/<your_quantity> command.
 - Refer to G4ScorerQuantityMessengerQCmd class.

Filter class


- G4VSDFilter
 - Abstract base class which you can use to make your own filter
- ```
class G4VSDFilter
{
 public:
 G4VSDFilter(G4String name) ;
 virtual ~G4VSDFilter() ;
 public:
 virtual G4bool Accept(const G4Step*) const = 0 ;
 ...
}
```
- Create your own messenger class to define /score/filter/<your\_filter> command.
    - Refer to G4ScorerQuantityMessenger class.



Define scorers to the tracking volume

Geant 4

# Class diagram



# example

```
MyDetectorConstruction::Construct()
{ ... G4LogicalVolume* myCellLog = new G4LogicalVolume(...);
 G4VPhysicalVolume* myCellPhys = new G4PVParametrised(...);
 G4MultiFunctionalDetector* myScorer =
 new G4MultiFunctionalDetector("myCellScorer");
 G4SDManager::GetSDMpointer()->AddNewDetector(myScorer);
 myCellLog->SetSensitiveDetector(myScorer);
 G4VPrimitiveSensitivity* totalSurfFlux = new
 G4PSFlatSurfaceFlux("TotalSurfFlux", fCurrent_In, "percm2");
 myScorer->Register(totalSurfFlux);
 G4VPrimitiveSensitivity* totalDose = new G4PSDoseDeposit("TotalDose");
 myScorer->Register(totalDose);
}
```

**You may register arbitrary  
number of primitive scorers.**


# Keys of G4THitsMap

- All provided primitive scorer classes use **G4THitsMap<G4double>**.
- By default, the copy number is taken from the physical volume to which G4MultiFunctionalDetector is assigned.
  - If the physical volume is placed only once, but its (grand-)mother volume is replicated, use the second argument of the constructor of the primitive scorer to indicate the level where the copy number should be taken.

e.g. `G4PSCellFlux(G4String name, G4String& unit, G4int depth=0)`

**Key should be taken from upper geometry hierarchy**

→ See exampleN07



- If your indexing scheme is more complicated (e.g. utilizing copy numbers of more than one hierarchies), you can override the virtual method **GetIndex()** provided for all the primitive scorers.

# Creating your own scorer

- Though we provide most commonly-used scorers, you may want to create your own.
  - If you believe your requirement is quite common, just let us know, so that we will add a new scorer.
- G4VPrimitiveScorer is the abstract base class.


```
class G4VPrimitiveScorer
{
public:
 G4VPrimitiveScorer(G4String name, G4int depth=0);
 virtual ~G4VPrimitiveScorer();
protected:
 virtual G4bool ProcessHits(G4Step*,
 G4TouchableHistory*) = 0;
 virtual G4int GetIndex(G4Step*);
public:
 virtual void Initialize(G4HCofThisEvent*);
 virtual void EndOfEvent(G4HCofThisEvent*);
 virtual void clear();

 ...
};
```

- GetIndex() has already been introduced. Other four methods written in red will be discussed at “Scoring 2” talk.

# G4VSDFilter

- **G4VSDFilter** can be attached to G4VSensitiveDetector and/or G4VPrimitiveSensitivity to define which kinds of tracks are to be scored.
  - E.g., surface flux of protons can be scored by **G4PSFlatSurfaceFlux** with a filter that accepts protons only.



# example...

```
MyDetectorConstruction::Construct()
{ ... G4LogicalVolume* myCellLog = new G4LogicalVolume(...);
 G4VPhysicalVolume* myCellPhys = new G4PVParametrised(...);
 G4MultiFunctionalDetector* myScorer = new G4MultiFunctionalDetector("myCellScorer");
 G4SDManager::GetSDMpointer()->AddNewDetector(myScorer);
 myCellLog->SetSensitiveDetector(myScorer);
 G4VPrimitiveSensitivity* totalSurfFlux = new G4PSFlatSurfaceFlux("TotalSurfFlux");
 myScorer->Register(totalSurfFlux);
 G4VPrimitiveSensitivity* protonSurfFlux = new G4PSFlatSurfaceFlux("ProtonSurfFlux");
 G4VSDFilter* protonFilter = new G4SDParticleFilter("protonFilter");
 protonFilter->Add("proton");
 protonSurfFlux->SetFilter(protonFilter);
 myScorer->Register(protonSurfFlux);
}
```






Accumulate scores for a run

Geant 4

# Class diagram



# Score == G4THitsMap<G4double>

- At the end of successful event, G4Event has a vector of G4THitsMap as the scores.
- Create your own Run class derived from G4Run, and implement **RecordEvent(const G4Event\*)** virtual method. Here you can get all output of the event so that you can accumulate the sum of an event to a variable for entire run.
  - **RecordEvent(const G4Event\*)** is automatically invoked by *G4RunManager*.
  - Your run class object should be instantiated in **GenerateRun()** method of your *UserRunAction*.

# Customized run class

```
#include "G4Run.hh"
#include "G4Event.hh"
#include "G4THitsMap.hh"
Class MyRun : public G4Run
{
public:
 MyRun();
 virtual ~MyRun();
 virtual void RecordEvent(const G4Event*);
private:
 G4int nEvent;
 G4int totalSurfFluxID, protonSurfFluxID, totalDoseID;
 G4THitsMap<G4double> totalSurfFlux;
 G4THitsMap<G4double> protonSurfFlux;
 G4THitsMap<G4double> totalDose;
public:
 ... access methods ...
};
```

Implement how you accumulate event data



# Customized run class

```
MyRun::MyRun() : nEvent(0)
```

```
{
```

```
 G4SDManager* SDM = G4SDManager::GetSDMpointer();
```

```
 totalSurfFluxID = SDM->GetCollectionID("myCellScorer/TotalSurfFlux");
```

```
 protonSurfFluxID = SDM->GetCollectionID("myCellScorer/ProtonSurfFlux");
```

```
 totalDoseID = SDM->GetCollectionID("myCellScorer/TotalDose");
```

```
}
```

name of *G4MultiFunctionalDetector*  
object



name of *G4VPrimitiveSensitivity* object

# Customized run class

```
void MyRun::RecordEvent(const G4Event* evt)
{
 nEvent++;
 G4HCofThisEvent* HCE = evt->GetHCofThisEvent();
 G4THitsMap<G4double>* eventTotalSurfFlux
 = (G4THitsMap<G4double>*)(HCE->GetHC(totalSurfFluxID));
 G4THitsMap<G4double>* eventProtonSurfFlux
 = (G4THitsMap<G4double>*)(HCE->GetHC(protonSurfFluxID));
 G4THitsMap<G4double>* eventTotalDose
 = (G4THitsMap<G4double>*)(HCE->GetHC(totalDose));
 totalSurfFlux += *eventTotalSurfFlux;
 protonSurfFlux += *eventProtonSurfFlux;
 totalDose += *eventTotalDose;
}
```

**No need of loops.  
+= operator is provided !**

# RunAction with customized run

```
G4Run* MyRunAction::GenerateRun()
{ return (new MyRun()); }

void MyRunAction::EndOfRunAction(const G4Run* aRun)
{
 MyRun* theRun = (MyRun*)aRun;
 // ... analyze / record / print-out your run summary
 // MyRun object has everything you need ...
}
```

- As you have seen, to accumulate event data, you do **NOT** need
  - Event / tracking / stepping action classes
- All you need are your **Run and RunAction** classes.



Refer to **exampleN07**